



Digitrax Command Control

450 Cemetery ST #206 Norcross, GA USA 30071  
(770)441-7992 FAX (770)441-0759  
Web Site: <http://www.digitrax.com>

## LocoPalm™ Cable for PDA

Enhance your Digitrax LocoNet® Operation

Use your PDA to run exciting LocoPalm™ Applications

### Choose the cable that fits your PDA

Cables available for many different models including  
Palm m100, m105, IIIc, IIIxe,  
VII & VIIx (with Click Encoder for speed and direction control);  
Handspring Visor, Visor Pro, Visor Prism & Visor Platinum  
and others to come

### Demo Software Disk Includes:

#### LocoMon LocoNet Monitor Demo Version

This peek tool lets you monitor LocoNet messages on the network.  
It's great for LocoNet debug and for LocoNet "Hackers".

#### LocoPalm™ Throttle Demo Version

Turns your PDA into a LocoNet Throttle! Just plug in to a Digitrax system & run trains!

F0-F12 function controls with Labels  
Switch Controls with Labels  
Easy to Understand Loco Keypad  
Buttons for Direction Control, Speed Control & Stop

**Note: LocoPalm™ & LocoMon Demo Apps will operate in demo mode until the registration code is entered.**

**Registration requires payment of an additional fee.  
Once registered, additional features are available.**

### Visit [www.locopalm.com](http://www.locopalm.com)

to register & learn more about the latest  
cool LocoPalm apps available.

Digitrax manuals & instructions are updated periodically.

Please visit [www.digitrax.com](http://www.digitrax.com) for the latest version.

These instructions were updated 01/02..

Made in USA



## LocoPalm™ Cable for PDA

### LocoPalm™ Instructions

#### A. Load applications to PDA

1. Copy demo files from floppy to the PC you hot sync with or download demo files to the PC from [www.locopalm.com](http://www.locopalm.com).
2. Hot sync with your PC to install applications on your PDA.
3. To convert from demo mode to full mode, follow the registration instructions at [www.locopalm.com](http://www.locopalm.com). There is an additional charge for registration.

#### B. Connect PDA to LocoNet®

1. Plug the appropriate LocoPalm™ Cable in to the bottom of your PDA.
2. Access the LocoPalm™ App you want to run.
3. Turn on your Digitrax LocoNet® System.
4. Plug the RJ12 end of the LocoPalm™ Cable into any LocoNet® jack on your Digitrax system.
5. Use the app you have chosen.

### Special Note for LPM100 & LPM100+

Some users find that the cable does not fit tightly enough to remain attached to the PDA unit during operation. If this is the case, you can improve the spring retention force as follows:

1. Strip the plastic jacket off a small piece of 22AWG wire.
2. Discard the wire.
3. Cut 2 short pieces of the plastic jacket -approximately 3/32".
4. Insert the pieces into the engagement tabs on the LPM100/LPM100+ plug as shown here.



### Visit [www.locopalm.com](http://www.locopalm.com)

to register & learn more about the latest  
cool LocoPalm apps available.